

How to Create Drive Image for Forensic Purpose using Forensic Replicator


June 3, 2015 By Raj Chandel

Forensic Replicator is a bit-stream forensic image creation tool. Forensic Replicator is a Windows based tool that creates bit-by-bit raw DD images of hard drives and related media. You can also create images in PFR format to encrypt the image, compress it, or break it up into smaller pieces. Forensic Replicator gives you everything you would expect in a forensic imaging tool.


Features

- Drive to Drive image option
- Creates bit-stream images of removable media, partitions, or an entire physical hard drive
- Creates images of USB micro drives
- New explore function allows for preview of active FAT files—tree and detail view available
- Allows for reprocessing of image files from Raw to Split or add compression as a new image file
- Compresses image files on the fly
- Encrypts data for secure storage of evidence-128 bit
- Splits images into segments for portability
- Generates self-extracting images
- Formats and copies DMF/1.68 MB floppy
- Creates ISO CDROM images and allows immediate browsing of data
- Automates floppy imaging with convenient Batch Assistant mode


First Download Forensic Replicator from **here** and install the Forensic Replicator.




Now click on file option & select create physical drive image




It will show creating physical drive image window. Click on next.




Now choose the drive of the Suspect Evidence you want to make image.



Now browse location and name of physical image file to create. Select save in raw format option. Click on next.



Select the file format such as Text File, Html File or Xml File. Select information for inclusion in the report i.e. Image information, Time and Date of Acquisition, Export Partition structure & Add report header & click on Next



Report Wizard

acquisition wizard

Select the report file format


- ☒ Text File
- ☐ Html File
- ☐ Xml File

Select information for inclusion in the report

- ☒ Image information
- ☒ Time and Date of Acquisition
- ☒ Export Partition structure
- ☒ Add report Header

< Back Next > Cancel Help

Now enter the details such as case no. , Evidence No. , Company /Agency etc. Click on Finish.



Report Header

acquisition wizard

Case No. 1

Evidence No. 1

Company/Agency Ignite Technology

Examiner Raj Chandel

Address1 Delhi

Address2


City State

Zip/Postal Country

Phone

< Back Finish Cancel Help

Now it will ask for File Name. Enter the file name & select the folder where report file is to be saved. Click on save.



Now it will create the raw image.

